INSERT FOR 1987 SWIFTAX 64 VERSION 1.0

This card contains additions and corrections to the enclosed user's manual. Please keep them together for future reference.

Very confusing

Installing SWIFTAX with Two Drives

The steps for installing SWIFTAX outlined on Pages 10-15 are designed for users with two single or dual (MSD) drives.

- Page 12—Step 6 should read, "Insert the SWIFTAX Program Disk Side 1 and press [C] to continue."

- When installing or running SWIFTAX, your Program Disk should be in drive 8 (drive 0 for a dual drive) and your data disk should be in drive 9 (drive 1 for a dual drive 0).

Follow the pages 10-15 in your manual to install SWIFTAX.

Installing SWIFTAX on a Single Drive

To install SWIFTAX on a single drive follow the instructions below.

1. Follow the instructions in your manual starting on Page 10 through Step 10 on Page 13 to make working copies of your SWIFTAX Disk, Sides 1 and 2.

2. When you have finished copying both Sides of the SWIFTAX disk, either with your own "Diskcopy" or the process described above, place your original SWIFTAX disk in a safe place.

11a

3. You must now make a second copy of SWIFTAX Side 1. Follow Steps (1-9) in your manual (Pages 10-13). Use SWIFTAX Program Side 1 as the "original" and a blank disk as the "duplicate." This new copy of SWIFTAX Side 1 will be modified by the INSTALL program to create your data disk. Be sure to leave this disk notched.

(over)

4. Label this blank disk as "Data."

5. Turn your computer off. Wait 15 seconds and turn it back on. Insert Side 2 of your working copy of the program disk into the drive and type **LOAD "INSTALL",8** and press [RETURN]. When you are asked about a back-up copy, press [Y] and press [RETURN].

6. CREATE NEW TAXPAYER FILE—Press [Y] and press [RETURN] if this is the first time you are running SWIFTAX or if you want to set up a new taxpayer (which requires a new data disk). Press [N] press [RETURN] if you only want to change the fast load status.

7. FAST LOAD—If you use an external speed loading device, press [N] and press [RETURN]. Otherwise, press [Y] and press [RETURN].

8. TAXPAYER FILE NAME—If you are only changing the fast load status, enter the name for your existing data disk. If this is a new data disk, enter a name (up to five characters long) and press [RETURN].

9. Insert a copy of Side 1 of your working Program Disk into the drive and press [C] to create the data disk onto which you will enter your tax return. When the INSTALL program has finished, you are ready to use SWIFTAX.